## **DIGIWTCP.EXE (NEW DRIVER)**

Driver to send/receive data to/from scales.

## **EXEcutable Type**

The format of the syntax is:

TWSWTCP command file num machine 1 [machine 2 ... machine n]

where the items inside the square backets are optional.

If an input/output file is needed, the format of the input/output filename is: SM + ip address or name + F + file number + .DAT

IP Address of Name: The full IP address of the scale. With this new driver no hosts file entry needed for the

scale definitions. File Number: If the file indicated as 25H (Hex value) in the driver manual, it will be used as 37 (decimal value of Hex(25))

See example below for the usage.

Example: machine dairy sending PLU records, the input file is

SMdairyF37.DAT command line is

TWSWTCP WR 37 dairy

Example: machine 192.168.1.2 sending PLU records from PC to scale,;

The input file name is: SM192.168.1.2F37.DAT

Upload command line is:

TWSWTCP WR 37 192.168.1.2

Input files should not have control characters embedded.

## **Parameters:**

Can be any of the following command

> RD - read WR - write DEL - delete DELFI - delete file

RD DEL - read and then delete

file number in decimal(base 10) form file num

machine 1 machine IP address and/or host name to operate on

[machine 2 machine n] additional IP addresses or host names to operate on

## **Returns:**

A file named result or the value of gcResult that contains the return code and the machine that returned the error. Format of the file is

1 of 2 15/12/2021, 15:50 machine\_1:return\_code;machine\_2:return\_code;machine\_n:return\_code.

return\_code - can be any of the following 0 = no error

- -1 = Open file error
- -2 = Read from file error
- -3 = Write to file error
- -4 = Network initialize error
- -5 = Network open error
- -6 = Network read error
- -7 = Network write error
- -8 = Machine read error
- -9 = Machine write error
- -10 = Machine no record error
- -11 = Machine space error
- -12 = Undefined error

2 of 2